



Instructions on how to mix the dry resins for Beva 371 a:

Package A contains:

Elvax Resin grade 150 500g
Aldehyde Resin 100g
Cellolyn 21 40g

Add Toluene 1000g

Heat in water bath (double boiler) until dissolved, stir from time to time.

Package B contains:

A-C Copolymer 400 170g
Paraffin (oil free, 65°C m.p.) 90g

Add Benzine (Naphtha) 500g

Heat in water bath until dissolved, then pour into the dissolved part A.
Stir well together, allow to cool slowly, in the double boiler, until the water is cold.

P.S. For the parts to be dissolved, each solution,
and then both together, must be above the cloud point, i.e. clear, with no lumps.